Animation Options

Set and test move animations here.

Animation			
	File		
Hit Box Definition Type:	Auto Map		•
Animation Clip:	Launcher		0
Preview Recorded Maps			
Hit Box Definition Type:	Custom		
Animation Clip:	Launcher		⊙
Custom Hit Boxes:		n Hit Boxes Info) 🤆	
oustonnin boxes.		n ne boxes into, e	
Wrap Mode:	Default		
Disable Head Look			
Apply Root Motion			
Lock X Motion			
Lock Y Motion			
Lock Z Motion			
	Speed		
Fixed Speed			
Base Speed:			
▼ Speed Key Frames			
U U	asting Timeline		
Casting Frame:	•	0	
New Speed:	1		
Frame Window (Aprox.):	30		
	•		•
Casting Frame: New Speed:	2	3	• •
Frame Window (Aprox.):	25		
i lane tinden (riprexi).			
	New Keyframe		
Original Frames:	80		
Time (seconds):	1.366667*		
Total frames:	56*	Apply	
	Blending		
Override Blending (In)			
Blend In Duration:	0		
Override Blending (Out)	⊽ ▼		
Blend Out Duration:	0.05		
	Orientation		
Mirror Animation (Left)			
Rotate Character (Left)			
Mirror Animation (Right)	-		
and a summation (ruging			
Rotate Character (Right)			
Rotate Character (Right)			
	Preview		
Character Prefab:			0
Character Prefab: Rotation Preview:	Preview		0
Character Prefab: Rotation Preview:	Preview	Z O	•
Character Prefab: Rotation Preview: X 0 Y	Preview	z 0	◎
Character Prefab: Rotation Preview: X 0 Y Anin	Preview © Robot_Kyle 90	z o	
Character Prefab: Rotation Preview: X 0 Y Anim Smooth Preview	Preview Robot_Kyle 90 nation Frames	z o	
Character Prefab: Rotation Preview: X 0 Y Anim Smooth Preview Animation Time:	Preview Preview Preview 90 Previe	z o	
Character Prefab: Rotation Preview: X 0 Y Anim Smooth Preview Animation Time:	Preview Robot_Kyle 90 nation Frames	Z O	
Character Prefab: Rotation Preview: X 0 Y Anima Smooth Preview Animation Time: Frame:	Preview Preview Preview 90 90 0.23333333 (17%) 13.7	Z 0	13.7

File

Animation Clip: The animation file (it's the file under your imported FBX file structure).

Wrap Mode: The animation wrap mode. Only works if *Animation Flow* is set to *Smoother* in the advanced options menu.

Disable Head Look: If enabled, will disable Head Look during this move.

Apply Root Motion: If enabled, the animation will have total control of the characters position in the field during its duration. When the animation is over, the engine will automatically re-adjust to new position and realign the Z axis. If you are using Mecanim, make sure you have the proper animation setup.

- Root Motion Node: If a body part is selected, after the animation ends the engine will attempt to force the character's position to the location of that part.
- Force Grounded: If toggled the character will automatically be brought back grounded on *Standing* state.

Speed

Fixed Speed: Toggle this option to have a fixed animation speed throughout the entire move.

Default Speed: The desired animation speed. Use negative numbers to make the animation play in reverse. When Fixed Speed is *disabled*, this the *initial* animation speed used in the keyframe timeline.

Speed Key Frames: Changes the animation speed at runtime, altering its frame data properties.

- Casting Frame: The frame in which the speed will change.
- New Speed: The new speed value.
- Frame Window (Aprox.): The amount of frames the animation will have in between this and the next key frame.

Animation Speed: The slider allows you to tune the speed of your animation, being negative or positive, while the blue bar shows how fast that animation will play out in the end. Negative speed will make your animation play in reverse.

Total Frames: Upon changing the speed of your animation (or using speed key frames), UFE will calculate (based on the FPS architecture of this move) how many frames it has. If you are satisfied with the results, click apply. Note: Make sure you set these before working with other frame options as changing these values will affect other frame data.

Blending

Override Blending (In): If enabled, this value will override the default blending value set for the character. Setting this value too high may affect the frame data of your move.

Override Blending (Out): If enabled, this value will override the default blending value set for the character when the animation ends.


Orientation

Set orientation and mirror settings for the move here.

Mirror Animation (Left): When character is on Left side, mirror the animation. **Rotate Character (Left):** When character is on Left side, rotate the character. NOTE: Setting both of the above effectively performs the Auto Mirror but without requiring the character to be on the other side.

Mirror Animation (Right): When character is on Right side, mirror the animation. **Rotate Character (Right):** When character is on Right side, rotate the character. NOTE: Setting both of the above effectively performs the Auto Mirror but without requiring the character to be on the other side.

Preview



Character Prefab: Drag your character prefab to this field in order to use the Animation Preview and Cinematics. This is only a preview reference for the move, the move does not require a prefab here.

Animation Preview: Preview the move animation as well as its hurtboxes. If you are using Mecanim animation, make sure the prefab has the Animator component attached with the correct avatar.

Notes:

• Make sure the prefab's animation type matches the animation clip's animation type (Legacy vs Mecanim), or the preview will not work.

Code example:

```
void OnHit(HitBox strokeHitBox, MoveInfo move, CharacterInfo hitter){
    Debug.Log("This move has a total of " + move.totalframes + " frames");
    Debug.Log("Startup frames: " + move.startupFrames);
    Debug.Log("Active frames: " + move.activeFrames);
    Debug.Log("Recovery frames: " + move.recoveryFrames);
}
```

< Back to Move Editor

From: http://ufe3d.com/ - Universal Fighting Engine

Permanent link: http://ufe3d.com/doku.php/move:animation?rev=1453097466



Last update: 2016/01/18 01:11