Character Editor

Here you can open an existing character info file or create a new one. Follow the instructions below to open Mike (character available on all versions):

Character Sample: `.\UFE\Characters\Legacy_Mike\Mike.asset`.
(SOURCE VERSION) Inherits from: `.\UFE\Scripts\CharacterInfo.cs`
(OTHER VERSIONS) Inherits from: `.\UFE\Plugins\UFE.dll\CharacterInfo`

To create a new character, in the project window click on `Create → U.F.E. → Character File`.

Set all the major variables a character has as well as their move sets and most importantly, the hitboxes.

Gameplay Type:

Portrail (small): Can be used in your own GUI. You can find an usage example on
.\Scripts\UI\Templates\DefaultCharacterSelectionScreen.cs

Portrail (big): Can be used in your own GUI. Code example at
.\Scripts\UI\Templates\DefaultCharacterSelectionScreen.cs.

Name: The name of the character.

Age: Age of this character. This, along with other information can be later displayed in a custom GUI.

Blood Type: The character's blood type (You never know when someone might need blood transfusion).

Gender: The character's gender.

Height: The character's height.

Life Points: How many life points this character has. If you are using percentage as damage to your moves, changing this has no impact on gameplay.

Max Gauge: The maximum amount of gauge (meter) this character can retain.

Alternative Color: In case of mirror match, the game will attempt on changing the rendered color of player 2 to this color.

Character Selection Animation: In case of using *3D character layout* for the character selection screen, select the animation that triggers when this character is selected.

Death Sound: If defeated, this sound will be played.

Description: Character description.

Sub-content:

- Character Prefabs
- Hit Box Setup
- Physics
- Head Look
- Custom Controls
- Gauge Display
- Move Sets
- AI Instructions (Fuzzy A.I.)

Video

[< Back to Universal Fighting Engine - Introduction](#)

From:
http://ufe3d.com/ - **Universal Fighting Engine**

Permanent link:
http://ufe3d.com/doku.php/character:start?rev=1667415515

Last update: **2022/11/02 14:58**

[< Back to Universal Fighting Engine - Introduction](#)